

How to submit the manifest in ASYCUDA WORLD

Establish the SSL connection to the server as directed. Once the connection is secured..

Type the URL <http://172.16.2.120:8081/awclient/> in the internet browser.

You will get the following web page

Sri Lanka Customs Document Processing Server

All entries to this server will be considered as finalized legal submissions, any cancellations should be approved by Sri Lanka Customs.

ශ්‍රී ලංකා රේගුව
Sri Lanka Customs இலங்கை சுங்கம்

Full Desktop (64 bit only)

ASYCUDA client runs on the most popular Java-enabled desktops such as Windows, Linux, Macintosh, Solaris, AIX and others and can be started from any web browser.

Full Desktop (32 bit only)

Use this connection if you have an old PC (32 bits).

Light Desktop

Tea Board and Boat Note offices

ASYCUDA offers rich client interfaces.
Full-fledged applications featuring secure e-Documents with rich client interfaces run on any Java-enabled computer connected to the network. They can be launched either from Web browsers such as Netscape Navigator or MS-Internet Explorer, or directly from an icon placed on the desktop.
Find out more about the background and origins of the ASYCUDA programme.

01 02 03 04 05 06 07 08 09 10 11

Select the relevant icon based on your computer (32/64 bit) and double click on the same.

Login using the username and the password issued by the Customs

Sri Lanka Customs Document Processing Server

All entries to this server will be considered as finalized legal submissions, any cancellations should be approved by Sri Lanka Customs.

ශ්‍රී ලංකා රේගුව
Sri Lanka Customs இலங்கை சுங்கம்

Full Desktop (64 bit only)

ASYCUDA client runs on the most popular Java-enabled desktops such as Windows, Linux, Macintosh, Solaris, AIX and others and can be started from any web browser.

Full Desktop (32 bit only)

Use this connection if you have an old PC (32 bits).

Light Desktop

Tea Board and Boat Note offices

ASYCUDAWorld

Login name

TL S_DHE_DSS_WITH_AES_128_CBC_SHA

01 02 03 04 05 06 07 08 09 10 11

You will get the following page



Document library

Document View Help

- ASYCUDA
 - Accounting & Payment
 - Cargo Manifest
 - Data Management
 - Manual Capture
 - XML Integration
 - Carrier
 - Degroupage**
 - Full Cargo
 - Printouts / Reports
 - Queries of Containers
 - Customs Headquarters
 - Goods Clearance
 - Integrated Tariff
 - References
 - Selectivity
 - Statistics
 - System Configuration
 - System Supervision
 - Transit
 - Transit Shed
 - International Norms
 - System Administration
 - System design
 - Tea Board
 - UN Ministry of commerce

 My Profile


Go to ASYCUDA

--Cargo Manifest

--Data Management

--XML Integration

If the xml is for a main line manifest click on the Full Cargo Integration




If it is for a second level manifest click on the Degroupage icon. Next locate the xml using the finder icon.



Click on the  icon to validate the xml. If any errors it will be displayed in the pdf format.

If the xml is validated without any errors click on  icon to upload the xml.


If errors following window will pop up



Click on  icon to retrieve the errors. Rectify the same. Upload the same again.


How to do a check BL.

Go to ASYCUDA--Cargo Manifest--Data Management--Manual Capture--Waybill.




Right click on the Waybill

The following window will popup.





Click on the  Find icon



Give the BL no and click on the finder  icon.

The following window will popup. Right click and View .



The relevant details appear. You can also view your own BLs.